


2.Windows GPS Support

- **Registering your GPS Maps [PC]**
 - **Registering your GPS maps MicroSD**
 - **Registering your GPS Maps Digital**
- **Installing Maps for Garmin Basecamp [PC]**
 - **Basecamp Map Installation [PC]**
 - **Unlocking Maps in Garmin Basecamp [PC]**
- **Updating Maps on Windows**
- **Troubleshooting GPS Maps**
- **Installing Backroad Maps Digital**

Registering your GPS Maps [PC]



Registering your GPS maps MicroSD



GARMIN
LICENSED TECHNOLOGY

BACKROAD GPS MAPS

BCAB BC & ALBERTA

ADVENTURE TOPOGRAPHIC MAPS

BONUS FREE APP ACCESS

PLUG & PLAY MICRO SD CARD

**FISH | HUNT | CAMP | HIKE
PADDLE | ATV | SNOWMOBILE**

MicroSD Insert the Micro SD card into the GPS unit

For units that use Regular SD Cards

SD Card Adapter

Insert the MicroSD card into the adapter, then insert the adapter into the GPS unit



REGISTER YOUR GPS MAPS

Technical guide – Backroad Map Books

1. Why Register Your MicroSD?

Feature	Description
Computer?based map downloads	Access to the latest <i>Computer Maps</i> for macOS & Windows.
Secure license storage	Keeps your <code>gmapsupp.unl</code> and <code>gmapsupp.gma</code> files safe in your account.

Feature	Description
Discounted updates	Receive future map releases at a reduced price.
Priority technical support	Faster response for any Garmin?map?related issue.

“ **Free Updates** – After registration you can download map updates for **60?days** at no charge. If you bought an older version from a retailer, you may upgrade to the latest map release within that 60?day window.

“ **Important:**

- A card that has already been registered **cannot** be registered again.
- If your card is “used” or already updated, the registration will fail.

2. Prerequisites


Step	Action	Notes
1	Insert the MicroSD card	<ul style="list-style-type: none"> • If your computer has an SD?card slot, insert the card directly. • If not, plug the card into your Garmin GPS and connect the GPS to your computer via USB.
2	Log in to Backroad Map Books	URL: https://backroadmapbooks.com/account/login Create an account if you do not already have one.
3	Locate the license files	The required files (<code>gmapsupp.unl</code> and <code>gmapsupp.gma</code>) are in the Garmin folder on your MicroSD.

3. Registration Workflow

“ All steps are performed on the *My GPS Maps* registration page.

3.1 Navigate to the Registration Page

1. After login, click the “**MY GPS MAPS**” button (top?right).
2. On the resulting page, select “**Register SD**”.



3.2 Upload the Unlock Code & GMA File


Field	File	How to select
Unlock Code (<code>gmapsupp.unl</code>)	<code>gmapsupp.unl</code>	Use the Choose File button to pick this file from the <i>Garmin</i> folder.
Gma File (<code>gmapsupp.gma</code>)	<code>gmapsupp.gma</code>	Use the Choose File button for the second field.

“ **Tip:**

Double-check that the files you pick are **exactly** the `.unl` and `.gma` files from the Garmin folder. Any mismatch will trigger an error.

3.3 Submit

1. Once both files appear in the form, click **SUBMIT**.
2. A green confirmation box will appear, and your product will be listed under “My Products”.



British Columbia Backroad 2025 GPS Maps NO UPDATES ▼

• Successfully registered product!

“ **Result:** The MicroSD card is now registered to your Backroad Map Books account.

4. Post-Registration

- **Access the “Computer Maps”** – Log in, go to **“My Products”** and download the latest PC? compatible maps.
- **Update within 60?days** – Download updates for free.
- **Backup your files** – Although the unlock codes are stored in the cloud, keep local copies of the `.unl` and `.gma` files on your computer for future reference.

British Columbia Backroad 2025 GPS Maps NO UPDATES ▼

Free Computer Maps ⓘ [View User Guide](#)

Click below to download

[Download for Mac](#) [Download for PC](#)

Register Date: 12/23/24, 10:01:46 AM PST
 Download Expiry Date: 2/23/25, 10:01:46 AM PST


Unlock your information ⓘ

Unlock Key: N0SN45P8PVWLZZQFH4LAGM4TT [Download](#)
 GMA File: [Download your GMA file](#)

ID Number: 35866
 ESN Number: 1000000000

4. Common Error Messages & Fixes

Error	Cause	Remedy
-------	-------	--------



“No ESN data found with unlockCode”	ESN (Electronic Serial Number) missing or corrupted.	Contact Backroad Map Books support (email: gps<at>backroadmapbooks.com).
“Invalid File Uploaded”	Wrong file type chosen (e.g., a <code>.zip</code> instead of <code>.gma</code> or <code>.unl</code>).	Re?select the exact <code>.gma</code> and <code>.unl</code> files from the Garmin folder.
“This card has already been registered”	Card was previously registered on another account or already updated.	Not recoverable – you must purchase a new card or contact support for advice.

5. Quick Reference

Action	Shortcut
Log in	<code>Ctrl+L</code> (Chrome)
Open registration	MY GPS MAPS ? Register SD
File picker	<code>gmapsupp.unl</code> ? Choose File; <code>gmapsupp.gma</code> ? Choose File
Submit	SUBMIT button

Prepared by the Backroad Map Books Technical Support Team

Registering your GPS Maps Digital



1. Overview

This guide explains how to register your digital map access code so you can:

- Download computer-compatible maps for macOS or Windows.
- Store a secure copy of your Garmin license/unlock files.
- Receive future updates at a discounted price.
- Access priority technical support.

“ **NOTE:** After registration, you receive **free map updates for 60 days**. Older versions purchased from a retailer can be upgraded to the latest maps within that 60-day window.

2. Registration Benefits

Benefit	Description
Computer-based map downloads	Get the latest map files for macOS and Windows.
Secure license storage	Your Garmin license/unlock files are safely stored in the cloud.
Discounted future updates	Pay less for subsequent map releases.

Free Updates:

You can download map updates **free of charge for 60 days** after the first registration of the MicroSD card.

3. Update & Upgrade Policy

Item	Policy
First-time registration	60-day free update period begins on the day you click <i>Submit</i> .
Subsequent upgrades	If you purchased a previous map edition from a retailer, you may upgrade to the newest edition within 60 days of the first registration.
After 60 days	Updates become paid and must be purchased through the Backroad Map Books website.

4. Important Warnings

“ Unit ID & Access Code

The 10-digit **UnitID** is required for digital map registration. It can be found under **Settings > About** on your GPS device.

3. Prerequisites


Item	Requirement	How to Obtain
MicroSD Card (Optional)	<i>If you choose to use a microSD card (not the physical memory).</i>	Insert into a GPS or computer with an SD reader.
ACCESS CODE	A unique alphanumeric code printed on the MicroSD packaging.	Look for the “ACCESS CODE” sticker on the card’s label.
UnitID	A 10-digit number that identifies your Garmin GPS.	Open the GPS <i>> Settings > About (or Device Info)</i> to view the UnitID.
Internet Connection	Required to submit the registration form and download computer maps.	Any reliable broadband or Wi-Fi connection.

4. Step-by-Step Registration

“ The following steps assume you have already plugged in your GPS so it is available and ready.

4.1 Log In to the Backroad Map Books Portal

1. Open a web browser and navigate to <https://backrockodmapbooks.com>
2. Click **Sign In** (top?right) and enter your account credentials.



4.2 Navigate to the Digital Map Registration Page

1. Once logged in, click **My Account ? Digital Maps ? Register Your Digital Map**.
![[Navigate to Digital Maps]](<https://brmb.support/uploads/images/gallery/2025-03/scaled-1680-reg.png>)

4.3 Enter the Registration Data

Field	Input	Example
Access Code	The code printed on the MicroSD card label.	BCBC-7r3325caa-8cec-483d-97db-059d88f78f29
UnitID	10?digit GPS unit identifier.	1234567890

“ The UnitID can be found under Settings ? About on your GPS.

Access Code: BCBC-7r3325caa-8cec-483d-97db-059d88f78f29
UnitID: 1234567890

“

REGISTER YOUR DIGITAL MAPS

STEP 1 - Enter access code

*Access Code (DVD ID)

BCBC-db2d2c0f-bab4-4500-9833-03adcb911911

(This is directly on your physical copy of the DVD)

STEP 2 - Enter GPS unit ID

*Unit ID

3928345911

[Where do I find this?](#)

Submit

4.4 Submit the Form

- Review the values you entered.
- Click **SUBMIT**.
- If registration succeeds, a green success message will appear and the new product will be listed under your account.

“

British Columbia Backroad 2025 GPS Maps


NO UPDATES

- **Successfully registered product!**

5. After Registration

- **Your digital maps are now registered** and available for download.
- The new product appears in the *My Gps Maps* section of your account.

- You can immediately start downloading the computer-ready map files.



6. Post-Registration Tasks

1. **Download the computer-ready map files:**
 - From your account, click **Download** next to the registered product.
 - Choose *macOS* or *Windows* as required.
 - Follow the on-screen prompts to install.
2. **Backup your license files:**
 - You can also download a copy of your Garmin license/unlock files from the portal for local backup.
3. **Schedule future updates:**
 - Within the 60-day free window, simply click **Get Updates** in the portal.

7. Troubleshooting

Symptom	Likely Cause	Fix
Registration fails with "Invalid Access Code"	Wrong Access Code or UnitID entered	Re-check the GPS UnitID.

Symptom	Likely Cause	Fix
Registration fails with “ <i>UnitID already registered</i> ”	The same UnitID was registered previously	Contact support; you may have a duplicate product or need to unlink the old registration.
Unable to download updates after 60 days	The free update window has expired	Purchase the latest map edition through the portal.
Green success box never appears	Browser security block (e.g., pop?up blocker)	Disable pop?up blockers or try a different browser.

8. FAQ

Q1. Can I use the Digital maps on multiple GPS devices?

A1. No – the registration is tied to your GPS UnitID, You can only load the maps on the registered GPS.

Q2. Do I need to install the Digital maps to a MicroSD card ?


A2. No, the Digital maps allow you to install the maps on the internal memory or your own microSD card.

9. Contact & Support

Channel	Availability	Notes
Email	Mon?Fri 9:00?17:00 PST	gps<at>backroadmapbooks.com
Phone	Mon?Fri 9:00?17:00 PST	(877)-520-5670

“ For urgent issues, reference the *UnitID* and *Access Code* in your support request.

Installing Maps for Garmin Basecamp [PC]



Basecamp Map Installation [PC]

Installing and Using Backroad MapBooks on a PC

1. Prerequisites

Item	What to do	Links
Garmin Basecamp	Install Basecamp to view and load maps.	Download Garmin Basecamp
7-Zip (optional)	If your OS can't extract ZIP files, install 7-Zip for free.	Download 7-Zip
Backroad MapBooks account	Sign up or log in to access your map downloads.	Backroad MapBooks Login
MicroSD card	Insert into the PC or GPS unit to access the unlock key (<code>.gma</code> file).	—

“ **Note** – All map files are delivered as a single `.zip` archive (e.g. `SECURED_BC2025_BRMB_BC2025?Win.zip`).

2. Downloading the Map Archive

1. Log in

- Navigate to the Backroad MapBooks website and sign in.
- If you don't have an account, click **Create New Account** and follow the prompts.

LOGIN

Email

customer@backroadmapbooks.com

Password

.....

[Forgot password](#)

Sign in

New customer? [Create an account](#)

2. **Navigate to “MY GPS Maps”**

- Click the **MY GPS Maps** button on the homepage to reach the registration page.

3. **Locate your product**

- Find the product title for your province (e.g., “BC2025”) and click the small arrow to the right of it to expand the product details.

British Columbia Backroad 2025 GPS Maps NO UPDATES

Your Maps are Up to Date [View User Guide](#)

We don't have any map updates at this time. [See complete version update list](#)

Map Update Available for Download

Download the 2025 GPS Maps Updater below:

Mac Updates PC Updates

Register Date: 3/24/25, 8:07:25 PM PDT
Update Expiry Date: 5/24/25, 8:07:25 PM PDT

The computer map links are only available for 60 days after your GPS Maps Registration or GPS Maps Update Purchase

Download Computer Maps (Free for 60 days) ⓘ

Click below to download the maps for Garmin Basecamp

Download for Mac Download for PC

Register Date: 3/24/25, 8:07:25 PM PDT
Download Expiry Date: 5/24/25, 8:07:25 PM PDT

The computer map links are only available for 60 days after your GPS Maps Registration or GPS Maps Update Purchase

4. Download the ZIP

- Click the **Download for PC** button and choose a location to save the file (the default is usually the **Downloads** folder).
- The download link will point to something like: `SECURED_BC2025_BRMB_BC2025?Win.zip`.

3. Extracting the ZIP Archive

1. Locate the file

- Open the folder where you saved the archive.

2. Extract

- **Windows** – Right-click ? **Extract All...**
- If you're using 7-Zip, right-click ? **7-Zip ? Extract Here.**

3. Verify extraction

- After extraction you should see a folder named similar to `SECURED_BC2025_BRMB_BC2025?Win` containing an installer executable and a copy of the .gpi file:
`BRMBBC2025_2025.exe` (replace `BC` with your province code).
`BC2025.gpi` (replace `BC` with your province code).

4. Installing and Unlocking maps in Basecamp.

1. Insert the MicroSD card


- If you have the MicroSD card inserted into the PC or your Garmin GPS and plugged into the computer.
- The card will appear as a removable drive (e.g., `E:`).

1b. Download your .gma

- If you Downloaded the .gma file from your account.
- The file will be downloaded to "Downloads" or the location you choose.


2. Launch the installer

- Double-click the executable (`BRMB####_2025.exe` , where `####` is your province code).
- A screen will appear guiding you through the installation, you can accept the default installation directory.
- A final screen will appear prompting you to provide a `.gma` file.



3. Select the `.gma` file

- **Option?A – SD File Select**
 - Pick your MicroSD drive from the drop-down list.
 - The installer will copy the unlock key to Basecamp automatically.
- **Option?B – Browse for file**
 - If the card isn't shown as a drive letter, click **Browse** and navigate to the card or to the location where the `.gma` file was downloaded from your account.



4. Complete the installation

- Click **Next ? Finish**.
- Basecamp will now contain the new map data.

5. Post-Installation

- **Launch Garmin Basecamp** – Verify that the new maps are visible.
- **Configure Basecamp** – Use the following resource for detailed configuration options:

<https://brmb.support/books/4configuring-garmin-basecamp>

6. Frequently Asked Questions


Question	Answer
<i>What if I can't find my MicroSD as a drive?</i>	Use the Browse for file option on the unlock screen to navigate to the card manually.
<i>Can I use the map on a mobile device?</i>	This guide is for PC only. For mobile devices see the BRMBMaps App .

7. Contact & Further Assistance

Need More Help?

- **Phone** – 1-877-520-5670
- **Submit Support Request** – > <https://backroadmapshelp.zendesk.com/hc/en-us/requests/new>

We're here to help you get your maps up and running as quickly as possible!




Unlocking Maps in Garmin Basecamp [PC]

“ If you skipped the `.gma` file during the initial map installation, you can manually import it to activate the maps.


1. Download the `.GMA` Unlock Key

Source	Where to Find It
From a device	Insert your microSD card ? open the <code>Garmin</code> folder on the card ? locate the <code>.gma</code> file (e.g., <code>gmapsupp.gma</code>).
From your account	Log in to your Backroad MapBooks portal ? download the <code>.gma</code> file you received during purchase.




2. Launch Basecamp

1. Start **Garmin Basecamp**.
2. If Basecamp detects any locked maps, a dialog will appear automatically.
 - Click **Unlock maps** to begin the process.
 - Screenshot:




“ If the dialog does not appear:
Open the Map Manager manually:

Maps ? Manage Map Products in the menu.




3. Import the .gma File

1. In the **Map Product Manager** window, click the **Unlock Regions** tab (top?left).




2. Click **Import**.

- A file?open dialog appears.
- At the bottom right, change the filter from `.ucx` to `.gma`.




3. Navigate to the `.gma` file:

- If you keep the key on your microSD card, browse to `E:\Garmin\` (or whichever drive letter your card is assigned).
- If you downloaded the key, go to the folder where you saved it.



4. Select the file and click **Open**.
5. Verify success – the map entry should now show something like “**Region unlock code from ...**” next to its name.



4. Refresh Basecamp

- Restart Garmin Basecamp.
- From the **Maps** menu, choose **Backroadmapbooks** to load the newly unlocked maps.

5. Need More Help?

- **Phone** – 1-877-520-5670
- **Submit Support Request** – > <https://backroadmapshelp.zendesk.com/hc/en-us/requests/new>

We're here to help you get your maps up and running as quickly as possible!


Updating Maps on Windows

“ **Prerequisite:** Your GPS Maps must be registered in the BackroadMaps account.

“ **Important:** Free update links are available only 60 days after registration.
Not registered yet? [Create an account here.](#)

1. Log in to Your BackroadMaps Account

1. Open a browser and go to [BackroadMaps](#).
2. Log in or create a new account.




The screenshot shows a login page with the following elements:


- LOGIN** (Large heading)
- Email** (Label)
- (Email input field)
- Password** (Label)
- (Password input field)
- [Forgot password](#) (Link)
- Sign in** (Orange button)
- [New customer? Create an account](#) (Link)

3. Click **MY GPS Maps** to reach the registration page.

Home > Account

ACCOUNT


 **Account Details**

 Order History

 My GPS Maps

2. Download the PC Updater

1. Expand the product details by clicking the down?arrow.

British Columbia Backroad 2025 GPS Maps NO UPDATES 1 

Your Maps are Up to Date [View User Guide](#)

We don't have any map updates at this time. [See complete version update list](#)


Map Update Available for Download

Download the 2025 GPS Maps Updater below:

[Mac Updates](#) [PC Updates](#)

Register Date: 3/24/25, 8:07:25 PM PDT
Update Expiry Date: 5/24/25, 8:07:25 PM PDT

The computer map links are only available for 60 days after your GPS Maps Registration or GPS Maps Update Purchase

Download Computer Maps (Free for 60 days) 


Click below to download the maps for Garmin Basecamp

[Download for Mac](#) [Download for PC](#)

Register Date: 3/24/25, 8:07:25 PM PDT
Download Expiry Date: 5/24/25, 8:07:25 PM PDT

The computer map links are only available for 60 days after your GPS Maps Registration or GPS Maps Update Purchase

2. Under **Map Updates Available for Download**, click **PC Updates**.

British Columbia Backroad 2025 GPS Maps NO UPDATES 

Your Maps are Up to Date [View User Guide](#)

We don't have any map updates at this time. [See complete version update list](#)

Map Update Available for Download

Download the 2025 GPS Maps Updater below:

[Mac Updates](#) [PC Updates](#)


Register Date: 3/19/25, 12:47:23 PM PDT
Update Expiry Date: 5/19/25, 12:47:22 PM PDT

The computer map links are only available for 60 days after your GPS Maps Registration or GPS Maps Update Purchase

3. Once the download completes, open the downloaded file **BRMB_updater2025.exe** (located where you saved it).





4. When prompted, click **Yes** to allow changes.



5. Follow the welcome wizard:

- Click **Next**.
- Accept the license agreement.







3. (Optional) Create a Backup

“ **Tip:** Backups protect your data in case the update fails. A folder named `Backup_BRMB` will appear on the Desktop and contain a copy of your current map data.

1. On the backup screen, choose your microSD card from the **Drive** drop-down.
2. Click **Backup**.






3. Wait patiently while the data is copied. Verify the files exist in the backup folder before proceeding.

?? Backup errors?

* The updater may take a while to copy large map files. * Do ****not**** interrupt the process.

4. Update the Maps

1. Select your microSD card again from the **Drive** drop?down.
2. Copy the new 25?digit unlock key displayed in the **Unlock Information** section.



3. Paste the key into the **Unlock Key** field.
4. Click **Update**.



Select your MicroSD card drive from the dropdown menu.
example: (BC2020)

AB2019 (F:) ▾

Enter the 25 digit unlock key from your BRMB user account.
*Your 25 digit unlock key is located under your registered product in your BRMB account.

G4K5WV5PS9MAYF7PWXX9FLQ88



Update

Help

< Back

Next >

Cancel



5. Verify the Update

1. Insert the microSD card into the GPS or connect the GPS via USB so the card appears as a drive.
Need help connecting your GPS? [Read our guide.](#)
2. After the update finishes, load the maps on your GPS.
3. Verify the map data by navigating on the device to **SETUP?>?MAP.**

6. Troubleshooting

If the update fails or maps don't appear correctly:

Check the detailed [Troubleshooting Steps for Windows GPS Maps](#).

7. Need More Help?

- Phone – 1-877-520-5670
- Submit Support Request – > <https://backroadmapshelp.zendesk.com/hc/en-us/requests/new>

We're here to help you get your maps up and running as quickly as possible!

Quick Reference

Step	Action
1	Log in ? MY GPS Maps
2	Download PC Updater
3	Backup (optional)
4	Copy unlock key
5	Run updater (<code>BRMB_updater2025.exe</code>)
6	Accept license, backup, then update
7	Verify maps on GPS

Troubleshooting GPS Maps

Troubleshooting Maps on your GPS

Check our [Compatibility List](#) to see if your unit is supported **Compatibility List**



Connecting your GPS to computer

When connecting your GPS to the computer you will need to use a USB cable.

When you plug your GPS into the computer it will put it into MASS STORAGE MODE allowing you to see the contents of the Device and the SD card inserted.

If your GPS unit is displaying an icon on the screen it usually indicates that it is connected correctly.

After a minute or so you will hear a ding or see a new drive letter show up under "This PC"



The GPS unit is not showing up when you plug it into the computer.

Some legacy Garmin outdoor handheld devices can be put into USB mass storage mode, turning the device into a card reader and allowing an inserted microSD card to be read by a computer. This card reader provides the ability to install detailed mapping to the device, in addition it provides the ability to locate active tracks that have been archived to the card. While in mass storage mode, these files can be viewed on the computer. However, there is no access to any data stored on the device itself while in this mode.

The following devices can be placed into mass storage mode:

- • **Astro 220***
- • **eTrex Legend Cx**
- • **eTrex Legend HCx**
- • **eTrex Venture Cx**

- • eTrex Vista Cx
- • eTrex Vista HCx
- • GPSMAP 60Cx
- • GPSMAP 60CSx
- • GPSMAP 76Cx
- • GPSMAP 76CSx
- • Rino 520HCx
- • Rino 530HCx

To put these devices into mass storage mode, follow the instructions below:

1. 1. Connect the device to the computer using the USB cable
2. 2. Go to the Main Menu
3. 3. Select Setup
4. 4. Select Interface
5. 5. Select USB Mass Storage Mode

Your device will now create a drive on your computer so you can access the data on your microSD card.

Maps do not show on GPS:

If the maps are not loading on the GPS and you are not getting an error message you can check the following.

- Re seat the card in the GPS
- Go to SETUP > MAP > Configure Maps/My Maps/Select Map

Different Units will have different option in the Map settings menu as shown above.

- Look for Backroadmapbooks in the map list and ensure it is set to enabled.

Adjust Map detail to the highest value under the same MAP settings

- Go to SETUP > MAP > Advanced Map Setup > Detail Level

Detail Level should be set to MOST for best results with our maps.

View the map on your GPS and zoom and pan to a new area and let the map render the detail for you.

Maps did not show in map list?

If your maps do NOT show up in the map list on your GPS you can try inserting it into the computer to view the contents of the card and verify the card is readable. The microSD card should contain a **GARMIN** folder with the following files and folder inside:

- POI [Folder] - contains the .gpi file that loads the points of interest write up information
- gmapsupp.img - Map data needed to view the map
- gmapsupp.unl - unlock key license to unlock the maps
- gmapsupp.gma - gma authentication license to authenticate the maps

Updated microSD cards will have a new 25 digit .gma file.
6UC7C710BP9KL7TMCX8S4J88.gma

example:

Overwritten SD Card:

Did you send anything to your unit? We recommend NOT sending any type of additional MAP DATA to the card. if you tried to send other maps to our card you may have overwritten the SD Card with alternate map data or licenses.

Garmin Maps & License files use the same name gmapsupp.* so when sending additional map data to the card it may overwrite our maps with the new map set your sending.

If you have overwritten your card you can try and rebuild it if you registered it in your account.

Defective Adapter:

If your Unit requires the bigger card and if you have a faulty adapter, the SD Card won't be read by the unit. Try a different Adapter if one is handy. Otherwise purchase a new one at any Superstore, Walmart, Futureshop, Best Buy.

Installing Backroad Maps Digital

Backroad Maps DIGITAL Maps are installed directly to your GPS unit memory, your own SD card or your Garmin Smart Watch

Building and installing your maps can be done using Garmin Basecamp and Mapinstall.


Connect your GPS to your computer

Connect GPS to computer


To Install your Backroad Maps Digital version you need Garmin Basecamp installed on your system and your Backroad GPS maps title installed and unlocked.

Install and unlock Maps in Basecamp

1.)Launch Garmin Mapinstall.




2.)Click Find Device or Select it from the drop down menu. Click continue.




3.)Use the Left mouse button to select the grid sections of the map you want to Build.

Use the right mouse button to de select the grids

Click Continue





4.) You will be shown the installation location and asked to confirm the installation.


Click Install to start installing the maps.

Installing to GPSMAP66 (E:\):

Map regions from these products will be installed on your device. This could take hours. Are you sure?


< Back

Install



5.)Click Finish to complete the map installation.

Inside the Garmin folder on your GPS or your microSD card you will see the map data "gmapsupp.img" and your gma license file.



The .gma license file will match the version of the maps it was installed from in Garmin Basecamp.

You can check this in Garmin Basecamp under


Maps > Manage Map Products > Unlock Regions

Updating your POI data


The Digital maps can be installed to the internal memory of your GPS unit or your own microSD card.

1.)If your Garmin folder does not contain a POI folder you can create one.

2.)When you downloaded the basecamp installation file it contains the updated .gpi file for your POI folder.



Copy the 2025.gpi file into the POI folder on your GPS or microSD card.



Disconnect and Reboot your GPS.

Verify that the maps are loaded by going to Setup menu and looking for BackroadMapbooks in the map list.